



# TUTORIAL



**PRAGMADEV**  
modeling and testing tools

<b>Introduction - - - - -</b>	<b>3</b>
<b>A simple system - - - - -</b>	<b>6</b>
<b>PragmaDev Specifier Tutorial - - - - -</b>	<b>7</b>
Organization .....	7
Requirements .....	8
Design .....	12
Simulating the system .....	26
Simulation options .....	26
Byte-code generation .....	26
The SDL simulator .....	29
Verifying the behavior .....	37
Prototyping GUI .....	40
GUI editor .....	40
Simulation .....	44
Conclusion .....	46
<b>PragmaDev Studio - - - - -</b>	<b>47</b>
Testing .....	47
Test case .....	48
Simulation against the SDL system .....	53
Code generation .....	55
Code generation options .....	55
Graphical debugging .....	58
Conclusion .....	62
<b>PragmaDev Developer Tutorial - - - - -</b>	<b>63</b>
Organization .....	63
Requirements .....	64
Design .....	68
Running the system .....	87
Generation profile .....	88
Compilation errors .....	91
The SDL-RT debugger .....	96
Verifying the behavior .....	105
Prototyping GUI .....	108
GUI editor .....	108
Simulation .....	112
Conclusion .....	113
<b>Automatic documentation generation - - - - -</b>	<b>115</b>
Publications .....	115
Documentation .....	121
Automatic generation .....	125

# 1 - Introduction


Before starting this tutorial, it is important to understand the basic concepts used in PragmaDev Studio. These concepts derive from the two languages supported by PragmaDev Studio, **SDL** and **SDL-RT**:

- SDL stands for **Specification and Description Language**. SDL is a graphical, object-oriented, formal language defined by the International Telecommunication Union - Telecommunication Standardization Sector (ITU-T) as recommendation Z100. The language is intended for the specification of complex, event-driven, real-time and interactive applications involving many concurrent activities that communicate using discrete signals.
- SDL-RT stands for **Specification and Description Language - Real Time**. It is a mix of SDL with another graphical language, UML, and of a textual language, C. It retains the graphical abstraction brought by SDL while keeping the precision of traditional techniques in real-time and embedded software development and making simpler the re-use of legacy code by using natively the C language. The object-orientation is also pushed a step further by using the UML diagrams.

The underlying concepts of both languages are the same: the overall application to develop is called the **system**. Anything that is outside the system is called the **environment**. The system itself is described via four complementary and consistent views:

- *Architecture*

A system can be decomposed in functional **blocks**. A block can be further decomposed in sub-blocks and so on until the functionality of the final blocks are simple enough. A block then fulfils its functionality with one or more **processes**, communicating with each other via **messages** (also called **signals**). A process is basically a task and has an implicit message queue to receive messages from other tasks. There is no need to define it. A block has no direct implementation in the final application; it is a matter of organizing and structuring the application. Blocks and process are called **agents**.




- *Communication*

Agents exchange messages through **channels**. Messages going through channels are listed to define the interface between the agents. When it comes to final code on the target, channels have no direct implementation; they are only used for structuring the software and defining the interfaces.

- *Behavior*

A process behavior is described graphically as a finite state machine. Internal process states, events (messages), decisions, timer manipulations, semaphore manipulations have specific symbols briefly summarized below necessary to understand the following tutorial:



SDL or SDL-RT procedures can be called within the process behavior description. In SDL-RT, C functions can be called as well; SDL also allows the call of C function via external operators or procedures.

- *Data and syntax*

This is where SDL and SDL-RT differ the most:

- In SDL, data is defined via **ADT (Abstract Data Types)**, using specific concepts and notations. The data manipulation has also a specific syntax, derived from languages such as Pascal.
- In SDL-RT, the C language is used to define and manipulate data, making things more familiar to developers.

Another SDL-RT specificity is the integration of UML use case and class diagrams for less time-critical parts of the system. Objects can be associated to processes or blocks and used in the behavioral parts of the processes.

In both SDL and SDL-RT models, PragmaDev Studio also integrates the Message Sequence Chart dynamic view. On such a diagram, time flows from top to bottom. Lifelines represent agents, semaphores or objects and key events are represented. The diagram emphasizes the sequence in which the events occur.

The two languages have each their specific domain of usage:

- SDL will be mainly used during the specification phase. Being formal, it also allows more possibilities of verification and testing.



## Tutorial

---

- SDL-RT will be mainly used in the development phase, since it is closer to the hardware on which the software will eventually run.

In addition to the full features PragmaDev Studio, there are also two variants of the tool that focus on each of these languages: **PragmaDev Specifier** for SDL modelling, and **PragmaDev Developer** for SDL-RT modeling.

Would you need any extra information on the diagrams and their meaning, the following references may be used:

- For SDL, the SDL Forum web-site has many tutorials and presentations:  
<http://www.sdl-forum.org/>
- For SDL-RT, the reference manual is available in PragmaDev Studio via the *Help / SDL-RT reference* menu. This manual is also available on the SDL-RT web-site:  
<http://www.sdl-rt.org>

## 2 - A simple system

The system we have chosen is simple enough to be written from scratch but rich enough to pinpoint the basics of SDL-RT and SDL. It is a very basic phone system composed of a central and of several phones. When the phones are created, the central gives them an automatically computed phone number. When a user takes a phone to call another one, the phone asks the central the id of the phone to be called identified by its phone number. The caller sends directly a call request to the distant phone. For simplicity sake the distant phone automatically answers.

This tutorial is divided into two parts, depending on the tool you will be using, or on the modelling language if you're using PragmaDev Studio:

- The tutorial for PragmaDev Specifier describes SDL modelling and starts on page 7.
- The tutorial for PragmaDev Developer describes SDL-RT modelling and starts on page 63.


The last part of this tutorial describes the automatic documentation generation (page 115). It is based on the SDL system but that can be applied to the SDL-RT example, and therefore will work in both variants of the tool.

If you do not want to design the example, you can find a complete project of this system in the examples under "Specifier/Tutorial" and "Developer/Tutorial".

## 3 - PragmaDev Specifier Tutorial

### 3.1 - Organization

Let's get our hands on the tool! Start *PragmaDev Specifier* (or *PragmaDev Studio* if this will be the application you will be using). The window that appears is called the Project manager:




*The Project manager window*


The project manager gathers all the files needed in the project. First let's create a new project with the *New project* button:



A window will pop up to set the project file name. Use the 'Browse' button to select the project's parent folder and name it "phone":




Click OK to create the project and open it:



*Phone empty project*


## 3.2 - Requirements

Let us express the requirements of our system with a Message Sequence Chart (MSC). To add an MSC, select the project, and click on the right mouse button. A contextual menu will appear:




*Add components to the project*

Select *Add child element* and the following window will appear:




The add component window

In *Requirements*, select *MSC* element and click on the *New* button. Go to the directory where your project is and type in "normal" with no extension. Click on save and you will get the following window:




Completed Add component window

Click Ok and the "normal" MSC appears in the "phone" project:




"normal" MSC in "phone" project

Double click on the MSC name or icon to open it. The MSC editor opens:



*The MSC editor*

Draw the following to express the requirements of our phone system:



*The "normal" MSC*

You will have to use the tool bar on the left. If you have any problem refer to the user's manual.

This MSC basically says the following:


- pCentral indicates the system has been initialized and is ready

- The initial global state is `Disconnected`
- The user represented as the environment (`RTDS_Env`) makes a request on the first phone `pLocal` to call the phone with the number 2
- The first `pLocal` asks the central the queue id of the phone with number 2
- The first `pLocal` uses the id to send a connect request (`sCnxReq`) to the second `pLocal`
- The second `pLocal` being disconnected, it confirms the connection (`sCnxConf`)
- The first `pLocal` tells the environment the call has succeeded
- The global system state is then considered `Connected`
- The user hangs up
- The first `pLocal` sends a disconnection request (`sDisReq`) to the second `pLocal`
- The second `pLocal` confirms disconnection (`sDisConf`) back to the first `pLocal`
- The first `pLocal` tells the environment the disconnection is confirmed
- The overall final state is back to `Disconnected`

You can write some other MSCs to get clearer ideas on what you want to do. Note the instances represented on the MSC can be any type of agent. Somehow you are roughly defining the first architectural elements. You can copy from the SDL/Tutorial example the "normal" and "busy" MSCs in the project to complete the description.


### 3.3 - Design

Let us now specify and design the system. As for creating an MSC, select *Add child element* on the project, then the *Active architecture* category in the dialog, and select *System* component. Note that the dialog will this time require to set a modelling language for the diagram. Choose *SDL Z100*:






After validating the dialog, the system appears in the project:



### "Phone" SDL system in the "Phone" project

Double click on the system name or icon to open the system diagram in the SDL editor:




### The SDL editor

The system will be divided into two main parts:

- The definition of the data types and messages we will use.
- The architecture in terms of processes.

To avoid mixing things, we will use partitions in the diagram. A partition is just a means to separate different kind of contents within a diagram; it is just a group of pages that can contain any symbol allowed in the diagram.


*PragmaDev Studio* has created the first partition for us, so let's use it to declare the types and messages we'll need:




### Declarations in the "Phone" system

You actually don't need to type the declarations completely, since PragmaDev Studio provides a way to directly insert skeletons for all kinds of declarations. To insert a skele-

ton, open the symbol text for modification, then right-click in the text box. The following menu appears:



After selecting the declaration kind, the skeleton is inserted in the symbol text:



Here are the data and types we need:


- The synonym declaration ("*Synonym (constant)*") in the "*Insert declaration*" menu) declares a constant for the maximum number of phones;
- The syntype ("*Syntype (constrained type)*") in the "*Insert declaration*" menu)

declaration declares a special type for the phone. This is basically an integer restricted to be between 1 and the maximum number of phones;

- The newtype declaration declares the type for the array of phone processes ("*Array' type (associative array)*" in the "*Insert declaration*" menu) ; the index is a phone number, and the value is a PID, which is a basic type in SDL, just as Integer.


The second declaration text box declares the signals that will be used in the system. They are mainly the ones we used in the MSC we created earlier, plus a few ones for error conditions. Three of the signals we declare have parameters: sCall, sGetId and sId. Note the sCall and sGetId signals use the PhoneNumberType type we've declared above.

Declaration skeleton insertion is not provided for signals, but PragmaDev Specifier will offer to auto-complete your code as you type. So for example, when declaring the sCall signal, if you start to type the signal parameter type, a list will appear under your text cursor listing all known types that start with the text you've already typed:



You can select one of the choices by using the up and down arrow keys, or by clicking on it in the list. Note that entities defined in a symbol are known only when the symbol has been validated, and if its syntax is correct.


Now let's design the architecture of the system. As we said, we'll use another partition, so let's create it first, using the new partition button in the partition tool-bar:



A new empty partition appears. What you've already done is of course not lost: you can go back to it using the other buttons in the partition tool-bar.

The system being very simple it will not require any block decomposition. The central will be a process as well as the phones. All the phones have the same behavior so they will be several instances of the same process. The phone system is therefore made of two pro-

cesses. For better legibility their name will be prefixed with a "p" because they are processes:




phone system view


Notes:


- This architecture is not strictly correct in regular SDL, since processes should not appear directly at system level. But PragmaDev Studio allows it, so let's keep things simple.
- To draw the cSelf channel keep the shift key down and click where the channel should break. To change the position of the channel, click on a segment, right-click on it and select *Set as text segment* in the contextual menu.
- Signals and the NUM\_PHONE constant have already been declared, and process names appear in the MSC. So their names will be auto-completed by PragmaDev Studio.

Since pCentral is making the link between the pLocal processes and considering the number of phones can be modified, pCentral will create all instances of pLocal. To represent that, the name pLocal is followed by the initial number of instances and the maximum number of instances we defined in the synonym in the other partition.

Messages to be exchanged between the processes are listed in the channels . To specify the incoming and outgoing messages in the diagram double click on the "[ ]" and type in between the square brackets. The channel going to the outer frame is implicitly connected to the environment. In the above example the channel cEnvLocal connects pLocal to the environment and defines sCall and sHangUp as incoming messages and sCallConf, sBusy and sHangUpConf as outgoing messages. The channel cEnvCentral connects pCentral to the environment and defines sReady as an outgoing message. The

cSelf channel has been created to represent messages exchanged between the different instances of pLocal.


Select pLocal and click on the right mouse button to open the process definition, or simply click on the  button that appears when you hover the mouse pointer over it:



### Contextual menu


Since the process is not in the project, it will be asked what type of element must be added. Keep the pre-selected options, *Process* element in *Behavior* and click OK.



A new window opens, showing the process definition. As for the system, the first partition has been automatically created:




*The process behavior description in SDL editor*

The first thing to design is the start transition. It is what the process will do as soon as it is created. In the case of pLocal process, we do nothing:





That transition means that once the process is started it will go to state **Idle**. Place a start symbol , keep it selected and click on the state symbol in the tool bar . The state symbol is automatically inserted and connected after the start symbol. An internal data

dictionary is updated on the fly to ease the writing of the process behavior. First create the Idle state definition: click on the State icon and put it in your diagram:




The state name is in edit mode so you can directly type Idle in it; but you may also use auto-completion to list the available choices for the state symbol.

Once the state has been defined, click on the input symbol  in the tool bar and the input message symbol will be automatically inserted below the state symbol. When you start typing, a list of all available messages will appear:



Select the `sCall` message and complete it with the correct parameter. This facility is context sensitive and works for almost everything: SDL keywords, agents, channels, signals, states, types, variables, timers, .... You can now finish the state description by yourself as explained below.

Considering the requirements described earlier, the `pLocal` process can either be asked to make a call by the operator or receive a call from another phone. The Idle state can therefore receive two types of messages described below:






## Tutorial


When receiving `sCnxReq` message, it will reply `sCnxConf` to the `sCnxReq` sender. To and sender are SDL keywords in the output symbol. The sender id is stored in the `remotePid` variable. The process then goes to `Connected` state.

If asked to make a call, the phone number to call needs to be retrieved. To do so, a variable of the correct type is given as parameter of the receiving message. It will be assigned when this message is received. Since `pLocal` has no idea how to address a phone number it asks the central process the process id of the called `pLocal` with the `sGetId` message. The `calledNumber` variable is re-used as is. No receiver is specified since the receiver process is completely determined by the system architecture. We may however have used `T0 pCentral` to specify it, or even to `parent` since `pLocal` was created by `pCentral`. The process then goes to `GettingId` state, waiting for the central to answer.

Once the pid of the remote phone is received from the central, it is stored in a local variable and the connection request message `sCnxReq` is sent. The process then goes into state `Connecting`. If the pid of the receiver was not found, the `sError` signal is received. A `sBusy` message is sent back to inform the user and the process goes back into state `Idle`:




Note the receiver for the `sBusy` message is specified by using `VIA cEnvLocal`. It means that the signal will be sent to the process at the other end of the channel `cEnvLocal`, connected to the process `pLocal` in the system diagram:




Since this channel is connected to the system's external frame, the signal will go to the environment. Please note specifying a receiver for `sBusy` is necessary here, since this signal may be sent not only to the environment, but also to the other `pLocal` processes in the system. If a receiver is not specified, the SDL semantics is to choose randomly a receiver among the available ones, so the signal may have been received by the wrong process.

Once the connection request has been sent, the remote process is either available and replies sCnxConf, or not available and replies sBusy:




Depending on the answer the resulting state is different.

Now that you have understood the basics of the finite state machine you can complete the process behavior:



As the description is done, the browsing window on the right side is updated allowing to quickly jump to a transition: just click on the transition. This is especially useful when the system gets big.




It is now time to declare variables in our process. To do so, the text symbol in the process behavior diagram is used. The declarations are introduced via the keyword DCL, followed by a list of couples <variable name> <variable type>, with an optional default value:

```
dcl
remotePID PID := NULL,
calledNumber Integer;
```


Just as for types, a skeleton for the declaration can be inserted via the contextual menu (entry 'Variables' in the 'Insert declaration' submenu). Note the type of the variable used in the input and output symbols for sCall and sGetId are not strictly the ones appearing in the definition: the signal declares a PhoneNumberType, but we use a regular Integer. This is no problem as long as the Integer satisfies the conditions set on the PhoneNumberType type.

Let's have a look at process pCentral now. It must do the following things:

- At startup, it creates all instances of pLocal and gives them a new phone number.
- When asked for a phone number, it sends back the pid for the corresponding process.

Go to the system diagram Phone, and open pCentral (via the contextual menu or the  button). Since the process is not in the project, it will ask if it should be added. Answer *Yes* and a pre-filled *Add child element* window with the process name appears. Click *OK*

and the process definition window appears. Let's first write the needed declarations and the initial transition:




The variables include an index which will be used as the phone number for created pLocal's, and an array mapping the phone number to the pid.

The initial transition creates all instances of pLocal within a loop testing `index <= NUM_PHONE`. Each time the loop is executed the pLocal process is created and its process id (offspring keyword for the parent process) is stored in the pLocals array, using the phone number as index.

After the pLocal processes creation, the sReady signal is sent to the environment to indicate initialization is finished and the process goes to state Idle.

Note we have voluntarily introduced an error by typing ";" instead of "," at the end of the first line in the lowest block of code to later show how to analyze the errors.



## Tutorial

---

The only request that can be received by pCentral process is sGetId. The phone number to reach is the parameter passed to the signal, which we will receive in the index variable. The process id of the phone is extracted from the array and sent back directly to the sender of the sGetId message (SDL keyword sender). If the phone number is out of range, an error message is sent back to the sender.


## 3.4 - Simulating the system

Now that the system has been designed, we'll debug it using PragmaDev Studio's SDL simulator. The simulation process is divided into two main phases:

- First, the code for all transitions in all system's processes is transformed into an internal representation called SDL byte-code. This language is used only internally and has no direct external representation.
- The generated byte-code is then executed based on a scheduling managed by PragmaDev Studio model debugger. The simulation conforms to the SDL semantics: all transitions are executed in no time and cannot be interrupted.


### 3.4.1 Simulation options

The Simulation options and the code generation options are edited via the *Generation / Options...* menu. By default a valid simulation profile is listed as well as an empty code generation profile:




As the simulation profile is the only valid debug profile, it will be used by PragmaDev Studio by default.

### 3.4.2 Byte-code generation

Select the Phone system in the project manager and click on the *Execute* quick button in the tool bar: 


A log window opens and displays the actions performed by the byte-code generator. Before actually generating anything, PragmaDev Studio performs a global syntax and semantics check on the written code. So any basic error such as typing mistakes or misspelling in variable names will be reported during this phase.

Since we introduced an error in process pCentral, this is what appears in the byte-code generator log window:




The byte-code generation started at system level, then went down in pCentral. During the generation for pCentral's start transition, the inversion between ";" and "," was encountered. So the generation stopped and this error message was displayed.

Double clicking on the error automatically opens the SDL editor and selects the symbol where the error occurred:




Once the error have been corrected the log window should look like this:





### 3.4.3 The SDL simulator

Once the byte-code generation is over, the SDL simulator window opens automatically:




*The SDL simulator window*


The simulator window shows a global state of the running system in terms of:

- Running processes
- Sent messages
- Started timers
- Local variables when in the context of a running process
- Watched variables, allowing to see the value of any variable at any time


The lower part of the window is a shell where actions taking place in the system will be reported.

Let's first run a MSC trace so that we can see graphically what is happening in the system.

Click on the *Start MSC trace* quick button:  A *MSC Tracer* window appears.

Now let's actually start the system by clicking on the *Run the system* quick button: 

Let the system run until all pLocal processes are created by pCentral and their start transition executed:



Note you can detach the execution buttons bar by dragging it away from its header (the zone looking like this: ):




*Detached execution buttons toolbar*

The environment is represented by the pseudo-process RTDS\_Env. This is not really a process as it does not appear in the list of running processes in the simulator window and


## Tutorial

has no code associated. It is only used to trace messages sent from and received by the environment.

Process `pCentral` dynamically creates 5 instances of `pLocal`, sends the `sReady` message to the environment and goes to state `Idle`. Each `pLocal` instance then goes to state `Idle`. On the left is the value of the system time. According to SDL semantics, all start transitions executed in no time, so the system time is still 0 after all processes have started.

Click on the *Stop* button to break execution: 

The SDL simulator window shows the list of all running processes, displaying for each one its name, process id, number of messages in its message queue and SDL state:




SDL simulator window


Now let's put a breakpoint in process `pCentral`:

- Open `pCentral` from the project manager.

- Go to the transition for signal `sGetId` in state `Idle` using the state / message browser:





or the *View* menu:




The state / message browser and the *View* / *Go to* menu allow to quickly navigate among the transitions defined in the process. Selecting the transition will automatically open the partition where the transition is and scroll to the corresponding signal input symbol.


- Click on the signal output symbol just after the decision's True branch:




- Click on quick-button  or go to *Debug / Set breakpoint* menu in the *SDL editor*. A breakpoint symbol is displayed on the side of the selected symbol:



We will now simulate an incoming message from a user:


- Go to the *SDL Simulator* and click on "Send an SDL message to the running system" quick-button 
- The *Send an SDL message* window shows up:



## Send an SDL message window


On the left are listed all possible receiving processes, in the middle all possible messages, i.e. all messages used in the SDL system, and on the right the value of the parameters associated with the selected message. Clicking on either the mes-

sage or the receiver will restrict the other list to show only the consistent choices. Here, we want to send a `sCall` signal, so let's select this signal in the list:



Since process `pCentral` cannot receive signal `sCall`, it disappears from the list of available receivers.


- Now let's select the signal receiver and input the called phone number, which should be passed as a parameter to the `sCall` signal:




The signal parameters are described in the right part of the signal send window. Double click on the parameter to edit its value and hit `<Enter>`.

- Click the *Send & close* button.
- Resume system execution by clicking the *Run* button in SDL simulator window.

- The following actions appear in the MSC trace:




- When the breakpoint is hit: the SDL editor then pops up and displays the symbol where the execution has stopped:




- Since we are in the context of a running process, local variables are automatically displayed in the SDL simulator window. All complex variables such as structs or arrays can be expanded to show their contents. Here are the local variables with the pLocals array expanded:


Local variables	Values
index (integer)	3
SENDER (pid)	2
PARENT (pid)	0
SELF (pid)	1
pLocals (pLocalArrayType)	
pLocals(1) (pid)	2
pLocals(2) (pid)	3
pLocals(3) (pid)	4
pLocals(4) (pid)	5
pLocals(5) (pid)	6
OFFSPRING (pid)	6


You can see the value for index is 3, so the value sent with the sId message will be the pid stored at index 3 in pLocals, i.e. 4.

- You can also execute instructions line by line in the symbols by using the *Flat step* quick-button: 



(NB: you may have to click on the button twice to go to the next state)  
The signal send has been done, as shown in the MSC trace:



- Let's now finish the system execution by pressing the *Run* button once more.
- When the signal *sCallConf* has been received by *RTDS\_Env* in the MSC trace, stop system execution with button 

The SDL states for all running processes are updated in the simulator window:

Name	Pid	Sig	SDL state
pCentral	1	0	Idle
pLocal	2	0	Connected
pLocal	3	0	Idle
pLocal	4	0	Connected
pLocal	5	0	Idle
pLocal	6	0	Idle

- The SDL state of a process can be dynamically changed using the contextual menu in the process list:


pCentral	1	0	Idle
pLocal	2	0	Connected
pLocal	3	0	Idle
pLocal	4	0	Connected
pLocal	5	0	Idle
pLocal	6	0	Idle

Connected  
 Connecting  
 Disconnecting  
 GettingId  
 Idle


Some caution is required with this feature, since it may have unexpected results on the system behavior...




- We will now disconnect the two connected pLocal processes by sending another signal. So press  once more:



This will send a sHangUp signal to the first pLocal (the receiver for our sCall message) with no parameters.


- Send the message with the *Send & close* button.
- We saw that stepping could be done at code line level. There are other step levels including:
  - Step at SDL event level with button 

This button will step one SDL event at a time. Click on it while looking at the MSC trace; you'll see that each time a SDL event happens (signal send, signal receive, process creation, timer start, and so on...), the system execution stops just after the event.
  - Step at transition level with button 


This button will execute a whole transition and stop just after its end (usually the next state symbol). Click on it while looking at the MSC trace; you'll see the active process execute all actions in current transition up to the state change, and the system execution stops.

### 3.4.4 Verifying the behavior

We will now check if the behavior is the one we expected in the first place. To do so we will use the MSC diff feature.


- Make sure the execution is over by clicking button  a last time. Then go to the MSC trace window, save the trace and close it.
- Close the simulator window.
- In the project manager, open the trace diagram.

- Go to the *Diagram / Compare with other diagram...* menu to get the MSC Diff configuration window and set it up as described below:




The first MSC is the trace and the second is the normal scenario we described in the first place. Since the normal MSC was not supposed to be thoroughly detailed we will only show and compare messages without considering their parameters.

Click *OK*; the following window appears:



It allows navigation through the differences between the MSCs. By selecting *All*, then all the differences will be shown in the diagram:



The only differences between the MSCs are the dynamic task creation of the pLocal instances. After that the exchange of messages are the same between the dynamic trace and the specification. The SDL system therefore conforms to the normal MSC specification.


This is the end of this very simple SDL simulation session. There are many areas that have not been covered, such as timers, procedures, external operators, system queue manipulations, watched variables, and so on... You may discover all these features yourself using the examples delivered in PragmaDev Studio distribution or by designing your own system.

## 3.5 - Prototyping GUI

PragmaDev Studio has a built in support to design simple prototyping interface to ease testing. We will build a very simple one for our phone system to demonstrate its capabilities.


### 3.5.1 GUI editor

Add a Prototyping GUI node in the project (category *Testing / Validation* in the *Add child element* dialog) and open it:




## Tutorial


The left panel contains the incoming triggers for the GUI, the central panel the GUI itself, and the right panel the outgoing message from the GUI:




Let's add 2 buttons and one LED:




Change their display value in the central panel and their widget name in the right panel in order to recognize them:




Let's say that when the user clicks on the "Call John" button, the GUI sends an sCall message with parameter set to "2". Select the CallJohn widget on the right panel and right click:




All the available messages in the system are then listed. Select `sCall` and expand the created sub-tree. The parameters are listed with their corresponding type:




Let's say the parameter value is '2' and let's send `sHangUp` without any parameter when clicking on Hangup:




On the left panel now, we will add a new trigger. A trigger performs some action on the widgets whenever a message is sent out of the system. Select the top of the tree and right click to get a list of all the possible triggers:




Let's add the `sCallConf` trigger. When a trigger is received by the GUI, a case with a set of filters is verified. Let's add a new case:




In our case we won't put any filter, we will just change the color of the LED:



The default action is DISPLAY; you'll have to right click on it to change it to CHANGE\_COLOR. The node in the tree under the action specifies the new color for the widget. It is possible to directly name the basic colors, otherwise the RGB hexa code can be used (e.g #FF8000 is **this color**). Let's put the LED back to red when we receive a HangUp confirmation and we're done:




### 3.5.2 Simulation


Let's start the Simulator again and click on the Start prototyping GUI quick button: 



The GUI will start and connect automatically to the system:



Start an MSC trace and run the system. Click on the "Call John" button, that should send the `sCall` message with parameter value set to 2, the `sCallConf` should be received by the GUI, and the LED should be set to green:



In practice, this is not a good example because there are a lot of different pLocal processes that could receive the messages sent by the GUI so the receiver is randomly selected.

For a more advanced GUI, please have a look at the AccessControl system in the Specifier example directory.

## 3.6 - Conclusion

During this tutorial we have been through:

- SDL,
- Project manager,
- SDL architecture & behavioral editors,
- MSC editor,
- SDL simulation including three stepping modes:
  - SDL code line,
  - SDL event,
  - transition,
- Conformance checking,
- Prototyping GUI.

As a result, you saw that SDL is perfectly suited to describe high-level specifications for real time systems. Its complete description covering architecture, behavior and abstract data types allows you to fully describe your system independently from the target implementation such as the processor, the RTOS or even the implementation language.


The following chapter will explore some PragmaDev Studio specific features such as testing and code generation.

## 4 - PragmaDev Studio

This chapter follows the PragmaDev Specifier Tutorial part. Please follow the previous chapter before continuing.


### 4.1 - Testing

PragmaDev Studio supports TTCN-3 standard testing language for edition and simulation. We will build up a small test case and run it on the phone system we have just designed. Let's add a TTCN-3 component to the project (category *Testing / Validation* in the *Add child element* dialog) and name it TestPhone:



### 4.1.1 Test case


The text editor recognizes the TTCN-3 syntax so all the keyword will be highlighted. Here is the test suite we will explain in the following paragraphs:




```


1 module TestPhone {
2
3   // Data types
4   type integer PhoneNumberType (1..5)
5
6   // The messages
7   type record sCall {
8     PhoneNumberType param1
9   }
10  type enumerated sHangUp { e_sHangUp }
11  type enumerated sBusy { e_sBusy }
12  type enumerated sCallConf { e_sCallConf }
13  type enumerated sHangUpConf { e_sHangUpConf }
14  type enumerated sReady { e_sReady }
15
16  // The ports
17  type port cEnvLocal_type message {
18    out sCall;
19    out sHangUp;
20    in sBusy;
21    in sCallConf;
22    in sHangUpConf
23  }
24
25  type port cEnvCentral_type message {
26    in sReady
27  }
28
29  // The SUT - System Under Test
30  type component Phone {
31    port cEnvLocal_type cEnvLocal;
32    port cEnvCentral_type cEnvCentral;
33  };
34
35  // Templates definitions
36  template sReady SystemIsReady := ?;
37  template sCallConf CallConf := ?;
38  template sBusy Busy := ?;
39  template sCall John := { param1 := 2 };
40
41  // the test cases
42  testcase tc_callJohn() runs on Phone
43  {
44    cEnvCentral.receive(SystemIsReady);
45    cEnvLocal.send(John);
46    alt
47    {
48      []cEnvLocal.receive(CallConf)
49      {
50        setverdict(pass);
51      }
52      []cEnvLocal.receive(Busy)
53      {
54        setverdict(fail);
55      }
56    }
57  }
58
59  // The control part
60  control{
61    var verdicttype verdict1;
62    verdict1 := execute(tc_callJohn());
63  }
64 }
65
  
```

C:\SDL\Tutorial\TestPhone.ttcn3 line 1 col 0 1305 bytes

To see a MSC representation of the TTCN-3 testcase behaviour, click on the View graphical representation button : 



You can select the functions and test cases you wish to visualise. In our simple case we will generate everything:



This MSC representation is not editable.

Since TTCN aims at testing complex systems, it is strongly structured. We first need to define the data types we will be using in our test case, define the interfaces with the system, and the value templates that will be exchanged.

#### 4.1.1.1 Declarations

The messages exchanged between the system and the environment are the ones listed in the channels connect to the frame of the system. Most of the message exchanged with the system have no parameters except sCall. sCall takes an integer sub-type as a parameter we will re-define here:

```
// Data types
```

```
type integer PhoneNumberType (1..5)
```

There is no message or signal specific type in TTCN: if the message has parameters it is defined as a record, and if it has no parameters, it is defined as an enumerated with a single possible value. Just as in symbols, skeletons for all kinds of declarations can be inserted in the TTCN file via the contextual menu, submenu '*Insert declaration*', then the declaration kind:

- "*'enumerated' type (enum)*" for enumerated types;
- "*'record' type (struct)*" for records.

Here are the TTCN declarations to create:

```
// The messages
type record sCall {
  PhoneNumberType param1
}
type enumerated sHangUp      { e_sHangUp }
type enumerated sBusy        { e_sBusy   }
type enumerated sCallConf    { e_sCallConf }
type enumerated sHangUpConf  { e_sHangUpConf }
type enumerated sReady       { e_sReady  }
```

### 4.1.1.2 Ports

TTCN-3 can test asynchronous systems, synchronous systems, or a combination of both. In our tutorial example only asynchronous messages are exchanged with the system. We will define a port for each channel in the system representing the 2 interfaces:

```
// The ports
type port cEnvLocal_type message {
  out sCall;
  out sHangUp;
  in  sBusy;
  in  sCallConf;
  in  sHangUpConf
}

type port cEnvCentral_type message {
  in  sReady
}
```

Just as for other declarations, a skeleton for a port type can be inserted via the contextual menu, then "*Insert declaration*", then "*Port type for asynchronous messages*".

We will now define the component we will be testing, that is the system itself. The name of the component must be the name of the SDL system.

```
// The SUT - System Under Test
type component Phone {
  port cEnvLocal_type cEnvLocal;
  port cEnvCentral_type cEnvCentral;
};
```

A skeleton for a component type definition can be inserted via the contextual menu, then "*Insert declaration*", then "*Component type*".

### 4.1.1.3 Templates

When exchanging messages with the system, the values of the parameters of the messages must be pre-defined. These values are called templates. Templates are used to both:

- define the values of the outgoing messages parameters,
- to verify the values of the received messages parameters are correct.

In our phone example, the messages coming from the system do not have any parameter, only the sCall message has one parameter. Still we need to define templates for all the message we will exchange with the system.

```
// Templates definitions
template sReady SystemIsReady    := ?;
template sCallConf CallConf      := ?;
template sBusy Busy              := ?;
template sCall John              := { param1 := 2 };
```

The John template will set the parameter of sCall to '2'.

### 4.1.1.4 Core test case

The core test case is the execution part, the scenario itself. To make it simple, we will first wait until the system sends the ready message on the cEnvCentral port, then we will call John and wait for the answer. An alternative is created: the call is confirmed and we will consider the test pass, or John is busy and we will consider the test fail:

```
// the test cases
testcase tc_callJohn() runs on Phone
{
  cEnvCentral.receive(SystemIsReady);
  cEnvLocal.send(John);
  alt
  {
    []cEnvLocal.receive(CallConf)
    {
      setverdict(pass);
    }
    []cEnvLocal.receive(Busy)
    {
      setverdict(fail);
    }
  }
}
```

A skeleton for a testcase definition can be inserted via the contextual menu, then "*Insert declaration*", then "*Testcase*". Note that the skeleton will also include a "system" clause that we are not using here, so it can just be deleted.

For the testcase body, it is also possible to insert a skeleton for the 'alt' block using the contextual menu, then "*Insert statement*", then "'alt' statement".



### 4.1.1.5 Control part


The control part is what will be executed, this is where you combine which test case you would like to run on the system. Please note there might be a different verdict for each test case. This won't stop the execution of the control part. In our tiny example we will just run the unique control part we wrote:

```
// The control part
control{
    var verdicttype verdict1;
    verdict1 := execute(tc_callJohn());
}
```

We're done with our test case, let's now run the test on the system and see what it does.


### 4.1.2 Simulation against the SDL system

Select the test suite in the project manager and click on the Debug button. In addition to the PragmaDev Simulator, the following window will open:



Please note it is possible to set breakpoints in the test case as well as in the SDL system.

Start an MSC trace, select the control part, and Run. The scenario will execute by itself and the verdict is displayed in the shell and in the MSC trace:




Because there are several instances of pLocal it might happen that the test case calls itself. In that case, run the scenario again for the test to pass.

## 4.2 - Code generation



### 4.2.1 Code generation options

It is possible to generate C code out of the SDL system in order to implement it on a real target. For this chapter, we will use our host computer as a target, and for that we will need a compatible debugger. MinGW is automatically installed on Windows and a compatible gdb version for Linux is available in the distribution. Please refer to the installation manual for further information.


The generation profiles are listed in *Generation / Options...*




The directory where the C files will be generated is automatically set to the ccg subdirectory under the project directory. Now we'll use the *Option wizard...* to quickly create a valid profile such as described below:




Make sure the "Generate environment process" box is checked.






### 4.2.2 Graphical debugging

Once the SDL debug profile is properly defined select the SDL system in the *Project manager* and click on the *Execute* quick button in the tool bar: 

Since several execution profiles are defined, a window pops up asking for the profile you want to work with:



```

Generation/build output

### Generating makefile...

### Updating packages for generated files...

### Compiling...
--- Changing directory to 'C:\SDL\tutorial\cc'
--- Running 'mingw32-make' *

mingw32-gcc -g -DRTDS_FORMAT_TRACE -f "H:\proj\dev\version5.3\srcs\releharc\ccg\windows" -fH:\proj\dev\version5.3\srcs\releharc\ccg\trace\formattrace -fH:\proj\dev\version5.3\srcs\releharc\ccg\common -g -DRTDS_SIMULATOR -DRTDS_CMD_INTERPRETER -fH:\proj\dev\version5.3\srcs\releharc\ccg\trace\command\cmdinterpreter -fC:\sd\tutorial -DRTDS_SOCKET_IP_ADDRESS=192.168.2.101 -DRTDS_SOCKET_PORT=49250 -c-o RTDS_utility_functions.o "C:\sd\tutorial\cc\RTDS_utility_functions.c"
mingw32-gcc -g -DRTDS_FORMAT_TRACE -f "H:\proj\dev\version5.3\srcs\releharc\ccg\windows" -fH:\proj\dev\version5.3\srcs\releharc\ccg\trace\formattrace -fH:\proj\dev\version5.3\srcs\releharc\ccg\common -g -DRTDS_SIMULATOR -DRTDS_CMD_INTERPRETER -fH:\proj\dev\version5.3\srcs\releharc\ccg\trace\command\cmdinterpreter -fC:\sd\tutorial -DRTDS_SOCKET_IP_ADDRESS=192.168.2.101 -DRTDS_SOCKET_PORT=49250 -c-o RTDS_encodedData.o "C:\sd\tutorial\cc\RTDS_encodedData.c"
mingw32-gcc -g -DRTDS_FORMAT_TRACE -f "H:\proj\dev\version5.3\srcs\releharc\ccg\windows" -fH:\proj\dev\version5.3\srcs\releharc\ccg\trace\formattrace -fH:\proj\dev\version5.3\srcs\releharc\ccg\common -g -DRTDS_SIMULATOR -DRTDS_CMD_INTERPRETER -fH:\proj\dev\version5.3\srcs\releharc\ccg\trace\command\cmdinterpreter -fC:\sd\tutorial -DRTDS_SOCKET_IP_ADDRESS=192.168.2.101 -DRTDS_SOCKET_PORT=49250 -c-o RTDS_Em.o "H:\proj\dev\version5.3\srcs\releharc\ccg\windows\RTDS_Em.c"
mingw32-gcc -g -DRTDS_FORMAT_TRACE -f "H:\proj\dev\version5.3\srcs\releharc\ccg\windows" -fH:\proj\dev\version5.3\srcs\releharc\ccg\trace\formattrace -fH:\proj\dev\version5.3\srcs\releharc\ccg\common -g -DRTDS_SIMULATOR -DRTDS_CMD_INTERPRETER -fH:\proj\dev\version5.3\srcs\releharc\ccg\trace\command\cmdinterpreter -fC:\sd\tutorial -DRTDS_SOCKET_IP_ADDRESS=192.168.2.101 -DRTDS_SOCKET_PORT=49250 -c-o RTDS_Start.o "C:\sd\tutorial\cc\RTDS_Start.c"
mingw32-gcc -g -DRTDS_FORMAT_TRACE -f "H:\proj\dev\version5.3\srcs\releharc\ccg\windows" -fH:\proj\dev\version5.3\srcs\releharc\ccg\trace\formattrace -fH:\proj\dev\version5.3\srcs\releharc\ccg\common -g -DRTDS_SIMULATOR -DRTDS_CMD_INTERPRETER -fH:\proj\dev\version5.3\srcs\releharc\ccg\trace\command\cmdinterpreter -fC:\sd\tutorial -DRTDS_SOCKET_IP_ADDRESS=192.168.2.101 -DRTDS_SOCKET_PORT=49250 -c-o RTDS_Central.o "C:\sd\tutorial\cc\RTDS_Central.c"
mingw32-gcc -g -DRTDS_FORMAT_TRACE -f "H:\proj\dev\version5.3\srcs\releharc\ccg\windows" -fH:\proj\dev\version5.3\srcs\releharc\ccg\trace\formattrace -fH:\proj\dev\version5.3\srcs\releharc\ccg\common -g -DRTDS_SIMULATOR -DRTDS_CMD_INTERPRETER -fH:\proj\dev\version5.3\srcs\releharc\ccg\trace\command\cmdinterpreter -fC:\sd\tutorial -DRTDS_SOCKET_IP_ADDRESS=192.168.2.101 -DRTDS_SOCKET_PORT=49250 -c-o RTDS_Shing.o "C:\sd\tutorial\cc\RTDS_Shing.c"
mingw32-gcc -g -DRTDS_FORMAT_TRACE -f "H:\proj\dev\version5.3\srcs\releharc\ccg\windows" -fH:\proj\dev\version5.3\srcs\releharc\ccg\trace\formattrace -fH:\proj\dev\version5.3\srcs\releharc\ccg\common -g -DRTDS_SIMULATOR -DRTDS_CMD_INTERPRETER -fH:\proj\dev\version5.3\srcs\releharc\ccg\trace\command\cmdinterpreter -fC:\sd\tutorial -DRTDS_SOCKET_IP_ADDRESS=192.168.2.101 -DRTDS_SOCKET_PORT=49250 -c-o RTDS_DS.o "H:\proj\dev\version5.3\srcs\releharc\ccg\windows\RTDS_DS.c"
mingw32-gcc -g -DRTDS_FORMAT_TRACE -f "H:\proj\dev\version5.3\srcs\releharc\ccg\windows" -fH:\proj\dev\version5.3\srcs\releharc\ccg\trace\formattrace -fH:\proj\dev\version5.3\srcs\releharc\ccg\common -g -DRTDS_SIMULATOR -DRTDS_CMD_INTERPRETER -fH:\proj\dev\version5.3\srcs\releharc\ccg\trace\command\cmdinterpreter -fC:\sd\tutorial -DRTDS_SOCKET_IP_ADDRESS=192.168.2.101 -DRTDS_SOCKET_PORT=49250 -c-o RTDS_TCP_Client.o "H:\proj\dev\version5.3\srcs\releharc\ccg\windows\RTDS_TCP_Client.c"
mingw32-gcc -g -DRTDS_FORMAT_TRACE -f "H:\proj\dev\version5.3\srcs\releharc\ccg\windows" -fH:\proj\dev\version5.3\srcs\releharc\ccg\trace\formattrace -fH:\proj\dev\version5.3\srcs\releharc\ccg\common -g -DRTDS_SIMULATOR -DRTDS_CMD_INTERPRETER -fH:\proj\dev\version5.3\srcs\releharc\ccg\trace\command\cmdinterpreter -fC:\sd\tutorial -DRTDS_SOCKET_IP_ADDRESS=192.168.2.101 -DRTDS_SOCKET_PORT=49250 -c-o RTDS_CmdInterpreter.o "H:\proj\dev\version5.3\srcs\releharc\ccg\command\cmdinterpreter\RTDS_CmdInterpreter.c"
mingw32-gcc -g -DRTDS_FORMAT_TRACE -f "H:\proj\dev\version5.3\srcs\releharc\ccg\windows" -fH:\proj\dev\version5.3\srcs\releharc\ccg\trace\formattrace -fH:\proj\dev\version5.3\srcs\releharc\ccg\common -g -DRTDS_SIMULATOR -DRTDS_CMD_INTERPRETER -fH:\proj\dev\version5.3\srcs\releharc\ccg\trace\command\cmdinterpreter -fC:\sd\tutorial -DRTDS_SOCKET_IP_ADDRESS=192.168.2.101 -DRTDS_SOCKET_PORT=49250 -c-o RTDS_FormatTrace.o "H:\proj\dev\version5.3\srcs\releharc\ccg\trace\formattrace\RTDS_FormatTrace.c"
mingw32-gcc -o Phone.exe RTDS_utility_functions.o RTDS_Em.o RTDS_Start.o RTDS_Central.o RTDS_Shing.o RTDS_DS.o RTDS_TCP_Client.o RTDS_CmdInterpreter.o RTDS_FormatTrace.o
H:\proj\dev\version5.3\srcs\releharc\ccg\windows\Phone\WinGll\rtows2_3a2

Close Save dialog text as...

```

PragmaDev Debugger

Debugger Options Windows Help »

Name Prio SDL id RTOS id Msg SDL-RT state System state

Time: 0

Timer info

Owner Name Time left


Semaphores SemId

Local variables Values

PragmaDev Studio shell

```
>Internal communication socket opened on port 49159
>Free run off.
>
```


Debugger state: STOPPED Active thread:

Click on the *Start MSC trace* quick button: 

An *MSC Tracer* window appears. Let's start the system; click on 'run' quick button:



The MSC Trace will look like the one below :




Click on the Stop button to break execution:





The SDL debugger window shows the list of processes with their names, priority, process id, queue id, number of messages in their respective message queues, SDL internal state as we defined in the diagrams, and the RTOS internal system state if available.



As with the SDL Simulator, it is possible to set breakpoints, view the value of variables, send messages... Would you like to know more about graphical debugging of C code, we strongly suggest to go through the PragmaDev Developer tutorial as the debugging features are the same.

## 4.3 - Conclusion

During this tutorial we have been through:

- Test of an SDL system,
- C code generation from an SDL system.

When it comes to design, the system will actually be implemented on a given target, so additional requirements will have to be taken into account:

- Use of legacy code and/or external libraries, usually written in C with no way to manipulate SDL's high-level abstract data types;
- Support for additional concepts, such as semaphores or pointers, unneeded in an SDL description, but usually required in real-time systems.


This is the aim of the SDL-RT language, which keeps the graphical description used in SDL but introduces the missing concepts required for low-level design.

So let's move on to the PragmaDev Developer tutorial!

## 5 - PragmaDev Developer Tutorial

## 5.1 - Organization

Let's get our hands on the tool ! Start *PragmaDev Developer* (or *PragmaDev Studio* if this will be the application you will be using).. The window that appears is called the Project manager:




### The Project manager window


The project manager gathers all the files needed in the project. First let's create a new project with the *New project* button:



A window will pop up to set the project file name. Use the 'Browse' button to select the project's parent folder and file name:




Let's set it to "phone":



phone empty project


## 5.2 - Requirements

Let us express the requirements of our system as MSC. To add an MSC, select the project, and click on the right mouse button. A contextual menu will appear:




Add components to the project

Select *Add child element* and the following window will appear:




The add component window

In *Requirements* category, select MSC component and click on the *New* button. Go to the directory where your project is and type in "normal" with no extension. Click on save and you will get the following window:




Completed Add component window

Click Ok and the "normal" MSC appears in the "phone" project:




"normal" MSC in "phone" project

Double click on the MSC name or icon to open it. The MSC editor opens:



*The MSC editor*

Draw the following to express the requirements of our phone system:



*The "normal" MSC*

This MSC basically says the following:


- pCentral indicates the system has been initialized and is ready
- The initial global state is disconnected
- The user represented as the environment (RTDS\_Env) makes a request on the first phone pLocal to call the phone with the number 0x02
- The first pLocal asks the central the queue id of the phone with number 0x02

- The first pLocal uses the id to send a connect request (conReq) to the second pLocal
- The second pLocal being disconnected, it confirms the connection (conConf)
- The first pLocal tells the environment the call has succeeded
- The global system state is then considered connected
- The user hangs up
- The first pLocal sends a disconnection request (disReq) to the second pLocal
- The second pLocal confirms disconnection (disConf) back to the first pLocal
- The first pLocal tells the environment the disconnection is confirmed
- The overall final state is disconnected

You can write some other MSCs to get clearer ideas on what you want to do. Note the instances represented on the MSC can be any type of agent or semaphore. Somehow you are roughly defining the first architectural elements. You can copy from the phone example "normal" and "busy" MSCs in the project to complete the description.


## 5.3 - Design

Let us now specify and design the system. As for creating an MSC, select the project and add a C header file component:







Project will be like:



This header file will contain all type and macro definitions to use in the whole system. What we need is the number of phones that will be created and a type for the phone number. So open common.h type its contents:


```
/* Number of phones to create */  
#define NUM_PHONE 5
```

Now, let us actually design the system itself. Select the project and add a System component. Make sure to select SDL-RT as the language for the system:



*"phone" SDL-RT system in the "phone" project*


Double click on the system name or icon to open the system diagram in the SDL-RT editor:



### The SDL-RT editor



The system being very simple it will not require any block decomposition. The central will be a process as well as the phones. All the phones have the same behavior so they will be several instance of the same process. The phone system is therefore made of two processes. For better legibility their name will be prefixed by a 'p' because they are processes.

Note: to draw the cSelf channel keep the shift key down and click where the channel should break.





*phone system view*

Since pCentral is making the link between the pLocal processes and considering the number of phones can be modified, pCentral will create all instances of pLocal. To represent that, the name pLocal is followed by the initial number of instances and the maximum number of instances. Since the maximum number of instances is defined in common.h, we include it in a text box.

Messages to be exchanged between the processes are defined in the additional heading symbol  and listed in the channels . To specify the incoming and outgoing messages in the diagram, click on the "[ ]" and type in between the square brackets. The channel going to the outer frame is implicitly connected to the environment. In the above example the channel cEnvLocal connects pLocal to the environment and defines call and hangUp as incoming messages and callConf, busy and hangUpConf as outgoing messages. The channel cEnvCentral connects pCentral to the environment and defines ready as an outgoing message. The cSelf channel has been created to represent messages exchanged between the different instances of pLocal.


In the message definitions, only the messages call, getId and idMsg have parameters. In our example process ids will be stored, so in order to design an RTOS independent model the RTDS\_PID type will be used. During code generation this type will be mapped to the real RTOS data type.

Select pLocal and click on the right mouse button to open the process definition, or simply click on the  button that appears near the symbol when hovering the mouse pointer over it:




Contextual menu



Since the process is not in the project it will ask if it should be added. Answer yes and an *Add child element* dialog pre-filled with the process name appears. Click OK and you end up in a new windows showing the process definition.




*The process behavior description in SDL-RT editor*

The first thing to design is the start transition. It is what the process will do as soon as it is created. In the case of pLocal process we do nothing:





That transition means that once the process is started it will go to state *idle*. Note you can use automatic insertion in the editor: place a start symbol , keep it selected and click on the state symbol in the tool bar . The state symbol is automatically inserted and connected after the start symbol.

An internal data dictionary is updated on the fly to ease the writing of the process behavior. First create the `idle` state definition: click on the State icon and put it at the top of your page:




The state name is in edit mode so you can directly type `idle` in it. Note that as soon as you start typing, PragmaDev Developer will display a list of choices for the state name, listing all those starting with the text you have already typed. To select one of the names, use the up and down arrow keys to browse the list, or click on it. Here, the list has only one entry because the `idle` state is the only one that has been defined so far.

Once the state has been defined, click on the input symbol  in the tool bar and the input message symbol will be automatically inserted below the state symbol. As for the state, the list of possible messages will appear as soon as you start typing. You can also press the F8 key to display the list of all possible messages:



Select the `call` message and complete it with the parameter as described below. This facility is context sensitive and works for messages, states, semaphores, and timers. You can now finish the state description by yourself as explained below.


Considering the requirements described earlier the pLocal process can either be asked to make a call by the operator or receive a call from another phone. The idle state can therefore receive two types of messages described below:




When receiving **conReq** message, it will reply **conConf** to the **conReq** sender. **TO\_ID** and **SENDER** are SDL-RT keywords in the output symbol. The **SENDER** id is stored in **remoteId** variable. The process then goes to **connected** state.

If asked to make a call, the phone number to call needs to be retrieved. To do so, a variable of the correct type is given as parameter of the receiving message. It will be assigned when this message is received. Since pLocal has no idea how to address a phone number it asks the central process the receiver queue id with the **getId** message. The **phoneNumber** variable is re-used as is and the **TO\_NAME** SDL-RT keyword is used to specify the receiver. Note **TO\_ID PARENT** could have been used since the central process is the current process's parent. The process then goes to **gettingId** state waiting for the central to answer. Note also that the memory allocated for **phoneNumber** memory will be freed by the receiver of the **getId** message.

Once the queue id of the remote phone is received from central, it is first stored in a local variable and the connection request message **conReq** is sent. The process then goes to **connecting** state. If the pid of the receiver was not found, the **errorMsg** message is received. The process tells the user (environment: **TO\_ENV**) and goes back to **idle** state:




The remote process is either available and replies conConf, or not available and replies busy:




Depending on the answer the resulting state is different.

Now that you have understood the basics of the finite state machine you can complete the process behavior:



As the description is done, the browsing window on the right side is updated allowing to quickly jump to a transition: just click on the transition. This is especially useful when the system gets big.





It is now time to declare variables in our process. To do so the text symbol in the process behavior diagram is used with standard C declarations in it:


```
RTDS_PID remoteId = 0;  
short phoneNumber;
```



Note the types of the variables used in the input and output symbols: `short` for `call` and `getId` and `RTDS_PID` for `idMsg`. `RTDS_PID` is the type for a process identifier; It is mapped to the corresponding RTOS-dependent data type.

Let's have a look at process `pCentral` now. It must do the following things:


- at startup, it creates all instances of `pLocal` and gives them a new phone number;
- when asked for a phone number, it sends back the queue id for the corresponding process.

To avoid mixing the code managing the phone numbers with the code managing the processes, let's decide we'll use a class associated to `pCentral` that will take care of the phone numbers.

The first thing to do is to tell pCentral that it should use a class. So, let's go back to the project manager with the  quick button and let's create a class diagram named telephoneLibrary in the project:



Double-click on the class diagram's name to open it and let's define a class associated to pCentral:



In a class diagram, the process pCentral is represented as an active class with a "graphical stereotype": the class symbol has bold borders and looks like a process symbol in a block diagram. Note the symbol used is a process symbol, not a process class symbol. That means the symbol is a direct reference to the process declared in the SDL system.

The class PhoneNumberFactory is the class we will use to manage the phone numbers. Its interface is quite simple:



- Its constructor (named <<create>> in the symbol) will just initialize all internal data, it takes the maximum number of phones to manage;
- The append method will add a new phone to be managed.
- The getPid method will return the process id for a given phone number.

The class PhoneNumberFactory will also have 2 private attributes:

- numPhone is the next available phone number;
- phoneList is a pointer on a process id. The process ids will actually be stored in an array.


Since there will only be one instance of PhoneNumberFactory used only in pCentral, we can make the instance a part of the process via a composition with a cardinality set to 1. The role name phoneId will identify the instance of PhoneNumberFactory in pCentral. That means phoneId does not need to be declared in the SDL diagram; it is implicitly declared.

To fill in the attributes and operations, you can either type the text, or select the class, click on the right mouse button and select *Properties*. The symbol properties will appear in the zone at the right of the diagram editor. There, you can click the *Structured edit* button, which will open a dialog allowing to add all the attributes and operations in a graphical way:



Now we have our class to manage the phone numbers. Of course, it isn't complete yet, since we didn't write any actual code for the methods. But its interface is fully defined, so we can go back to our pCentral process.

Go to the system diagram phone, and double click on pCentral. Since the process is not in the project it will ask if it should be added. Answer *yes* and a pre-filled save window with the process name appears. Click *OK* and the process definition window appears. First, its initial transition:




The first thing to do is to create the instance of `PhoneNumberFactory` we will use. This is done via an object initialization symbol, where the instance `phoneId` (the name we set in the role in the class diagram) is created as an instance of `PhoneNumberFactory`. The class constructor takes the maximum number of phones to handle as a parameter. Again, because of the association between `PhoneNumberFactory` and `pCentral` classes, `phoneId` is implicitly declared in `pCentral` SDL behavior diagram.

Then, all instances of `pLocal` are created in a loop testing `index < NUM_PHONE`. Each time the loop is executed the `pLocal` process is created and its process id (`OFFSPRING` keyword for the parent process) is stored in `phoneId` object via the `append` method.


After the `pLocal` processes creation, the `ready` message is sent to the environment to indicate initialization is finished and the process goes to state `idle`.

Note we have intentionally introduced a C syntax error by forgetting ";" in the lowest block of code to later show how to analyze the compiler errors.




The only request that can be received by pCentral process is getId. The phone number to reach is the GetId parameter (phoneNumber). The process id of the phone is extracted with the getPid method. When received, the index corresponding to the received phone number is searched via the getPid method on the PhoneNumberFactory instance. The answer is sent to SENDER (SDL-RT keyword in output). If the phone number is out of range, an error message is sent back to the sender.

Now, let's go back to our class PhoneNumberFactory: we could write the .h and .cpp files directly, but PragmaDev Studio can help. So go back to the project manager, select the phone system, and select *Generate classes code...* in the *Generation* menu. A log window will then list the operations made during the code generation, which should run without errors.




Now let's close the log window and go back to the project manager:



RTDS class sources package has been automatically created and contains C++ code generated from the classes defined in the project.

RTDS class sources should contain the .h and .cpp files for the class PhoneNumberFactory. Open PhoneNumberFactory.h:




```
1  #ifndef _PHONENUMBERFACTORY_H
2  #define _PHONENUMBERFACTORY_H
3
4  // Forward declaration (the following includes may use the class)
5  class PhoneNumberFactory;
6
7
8  // Standard and common includes
9  #include "common.h"
10 #include "RTDS_gen.h"
11
12 // Includes for related classes
13
14 #include "RTDS_messages.h"
15
16
17
18
19 // CLASS PhoneNumberFactory:
20 // =====
21
22 class PhoneNumberFactory
23 {
24
25 // ATTRIBUTES:
26 // -----
27
28 private:
29     short    numPhone;
30     RTDS_PID* phoneList;
31
32 // OPERATIONS:
33 // -----
34
35 public:
36     PhoneNumberFactory(short maxPhone);
37     virtual short    appen(RTDS_PID pid);
38     virtual RTDS_PID getPid(short phoneNum);
39
40 };
41
42
43 #endif
44
```

Since the file `common.h` has been defined at the project level, it is supposed to be needed everywhere in the project. So it has been automatically included in the generated header file. `RTDS_gen.h` is a generated file containing declarations specific to the system. The class definition then contains all attributes and operations we entered in the class diagram.

Please note this header file must not be modified manually: it will be re-generated each time a code generation is made.




Now open `PhoneNumberFactory.cpp`:



Skeletons for the constructor and the two methods defined for `PhoneNumberFactory` have been generated. Note the C++ code browsing window on the right to quickly access operation definitions. The generated code also includes as a comment the attributes definitions.

Now you can enter the code for the methods:



```
PragmaDev Studio - Text files
File Edit Search Preferences Windows Help »

* PhoneNumberFactory.cpp
#include "PhoneNumberFactory.h"

/*
 * ATTRIBUTES FOR CLASS:
 * -----
 *
 * [From PhoneNumberFactory]
 * - short numPhone;
 * - RTDS_PID* phoneList;
 */

// PUBLIC OPERATIONS:
// =====

// Operation PhoneNumberFactory:
// -----

PhoneNumberFactory::PhoneNumberFactory(short maxPhone)
{
    numPhone = 0;
    phoneList = (RTDS_PID*)RTDS_MALLOC(maxPhone * sizeof(RTDS_PID));
}

// Operation append:
// -----

short PhoneNumberFactory::append(RTDS_PID pid)
{
    phoneList[numPhone] = pid;
    numPhone++;
    return numPhone - 1;
}

// Operation getPid:
// -----

RTDS_PID PhoneNumberFactory::getPid(short phoneNum)
{
    return phoneList[phoneNum];
}

C:\Users\erich\Documents\PragmaDevStudio\Tutorial\Developer\ line 42 col 28 679 bytes
```

Right-hand pane content:

```
PhoneNumberFactory
  PhoneNumberFactory(short)
  append(RTDS_PID)
  getPid(short)
```

numPhone represents the next available phone number. The append method stores the process id in the phoneList array with index numPhone.

Please note that once the .cpp file exists, it will not be overwritten by the next code generation. So the code you've written will be kept as long as you don't manually erase the file.

## 5.4 - Running the system

In the current release, execution and debug of the system can be done using:

- Wind River Tornado environment on Windows or Solaris, or
- Posix and gdb integration on Linux or Solaris, or
- Win32 and gdb or MinGW integration on Windows, or
- CMX RTX and Tasking Cross View Pro debugger on Windows, or
- OSE and gdb debugger on Windows, or
- Nucleus and gdb debugger on Windows.

It is important to understand integration is done at two different levels:


- **RTOS integration**  
The generated code is based on C macros that are defined in the "Code template directory" to call the corresponding RTOS system primitives. Currently there is a directory for:
  - VxWorks,
  - Win32,
  - Posix,
  - CMX RTX,
  - OSE Delta,
  - OSE Epsilon
  - ThreadX,
  - uITRON 3,
  - uITRON 4,
  - Nucleus.
- **Debugger integration**  
To be able to trace execution, set breakpoints and view variables, the SDL-RT debugger is interfaced with a C debugging environment. Depending on the C debugger functionalities there might be differences in the SDL-RT debugger. The available C debugger interfaces are:
  - Tornado
  - gdb (Gnu debugger)
  - MinGW (Minimalist GNU for Windows)
  - Tasking Cross View Pro  
*Tasking* integration has one major restriction: it is not possible to send an SDL-RT message to the running system from the debugger.
  - XRAY  
As with *Tasking* integration: it is not possible to send an SDL-RT message to the running system from the debugger.
  - Multi 2000  
As with *Tasking* and *XRAY* integrations, it is not possible to send an SDL-RT message to the running system from the debugger.

The rest of the tutorial will use your host environment as a target (windows or posix integration) and gdb as a debugger.


Please note win32 and posix integrations use a socket to communicate with the host. The default port set to 49250 but it can be modified in the *Socket port num* field of the corresponding generation profile.

### 5.4.1 Generation profile

Now that the system is designed, let's debug it with the SDL-RT debugger. To do so we will need to generate code from the SDL-RT system. This requires to define a set of generation options, which is done via the *Generation / Options...* menu:




Rename the default empty profile and use the *Options wizard* to quickly set up a working profile:





You'll have to check that everything is setup properly, and also to change a few things in the created options:

- The destination directory should be set to ccg. This directory is relative to the project directory, and will be created if it doesn't exist yet, so no need to create it explicitly.
- Since we're using C++, the compiler has to be changed, the default one being a C compiler (in the build tab). The correct value is:  
mingw32-g++
- Make sure the C++ include path option includes the upper directory because the common.h file is in the project directory and the generated C files are in ccg. So the compiler options must include:  
-I . .


Here is how the 3 tabs should look like in the final set of options:






*Gnu example on Windows platform*


### 5.4.2 Compilation errors

Once the SDL-RT debug profile is properly defined select the phone system in the *Project manager* and click on the *Debug* quick button in the tool bar: 


If several execution profiles are defined, as in the examples, a window pops up asking for the profile you want to work with:



The first the tool will ask about the target directory:




*PragmaDev Studio* will compare the dates of the generated C/C++ files with the dates of the project, the diagram, the preferences. If the generated C file are not up to date the following window will pop up to confirm the code should be generated again or not.



This is very useful with large projects to avoid long compilations.


The package `RTDS` generated code is automatically created in the Project manager window that will contain all the generated C files.



The package `RTDS` `RTOS` adaptation is automatically created in the Project manager window that will contain all the C files needed to adapt to the selected RTOS. These files are actually in the code templates directory defined in the generation profile. These files are normally not needed but since they are part of the build process they must be visible. The package `RTDS` `class` sources is also re-generated, but all the existing `.cpp` files are left as is.




Syntactic verification, semantic verification, code generation, and compilation starts: Let's consider an error occurred while designing pCentral process. The compiler will complain in the *Generation / compilation output* window:




```
### Generating code...
--- Checking syntax/semantics for 'sPhone'
--- Checking syntax/semantics for 'pLocal'
--- Checking syntax/semantics for 'pCentral'
### Generating makefile...
### Updating packages for generated files...
### Compiling...
--- Changing directory to C:\SDL\Tutorial\Developer\ccg
--- Running "mingw32-make "
mingw32-g++ -DRTDS_FORMAT_TRACE -I." -I'h:\project\versions\5.3a\rtids_rellshare\ccg\windows" -I'h:\Project\Versions\5.3a\rtids_rellshare\ccg\trace\formattrace"
-I'h:\Project\Versions\5.3a\rtids_rellshare\ccg\common" -g -DRTDS_SIMULATOR -DRTDS_CMD_INTERPRETER
-I'h:\Project\Versions\5.3a\rtids_rellshare\ccg\trace\commandinterpreter" -I'c:\sdltutorial\developer" -DRTDS_SOCKET_IP_ADDRESS=192.168.2.101
-DRTDS_SOCKET_PORT=49250 -I.. -c -o "pCentral.o" "c:\sdltutorial\developer\ccg\pCentral.c"
c:\sdltutorial\developer\ccg\pCentral.c: In function 'void pCentral(RTDS_GlobalProcessInfo*)':
c:\sdltutorial\developer\ccg\pCentral.c:86:7: error: expected ';' before 'index'
    index++
      ^
Makefile:49: recipe for target 'pCentral.o' failed
mingw32-make: *** [pCentral.o] Error 1
!!! Compilation failed (error code 512)!
### Done.
```

Close Re-compile Save dialog text as...

Double click on the desired warning or error to automatically open the SDL-RT editor on the error (please note this is only available with gcc based compilers):



Once the error have been corrected the *Generation / compilation output* window should look like this:



```

mingw32-g++ -DRTDS_FORMAT_TRACE -I" -Ih:\project\versions\5.3\rtids_rellshare\ccgl\windows" -Ih:\Project\Versions\5.3\rtids_rellshare\ccgl\trace\formattrace"
-Ih:\Project\Versions\5.3\rtids_rellshare\ccgl\common" -g -DRTDS_SIMULATOR -DRTDS_CMD_INTERPRETER -Ih:\Project\Versions\5.3\rtids_rellshare\ccgl\trace\commandinterpreter"
-Ic:\sd\tutorial\developer -DRTDS_SOCKET_IP_ADDRESS=192.168.2.101 -DRTDS_SOCKET_PORT=49250 -I. -Wwrite-strings -c -o "pl.o" c:\sd\tutorial\develop\ccgl\pl.o.c"

mingw32-g++ -DRTDS_FORMAT_TRACE -I" -Ih:\project\versions\5.3\rtids_rellshare\ccgl\windows" -Ih:\Project\Versions\5.3\rtids_rellshare\ccgl\trace\formattrace"
-Ih:\Project\Versions\5.3\rtids_rellshare\ccgl\common" -g -DRTDS_SIMULATOR -DRTDS_CMD_INTERPRETER -Ih:\Project\Versions\5.3\rtids_rellshare\ccgl\trace\commandinterpreter"
-Ic:\sd\tutorial\developer -DRTDS_SOCKET_IP_ADDRESS=192.168.2.101 -DRTDS_SOCKET_PORT=49250 -I. -Wwrite-strings -c -o "RTDS_OS.o"
h:\project\versions\5.3\rtids_rellshare\ccgl\windows\RTDS_OS.c"

mingw32-g++ -DRTDS_FORMAT_TRACE -I" -Ih:\project\versions\5.3\rtids_rellshare\ccgl\windows" -Ih:\Project\Versions\5.3\rtids_rellshare\ccgl\trace\formattrace"
-Ih:\Project\Versions\5.3\rtids_rellshare\ccgl\common" -g -DRTDS_SIMULATOR -DRTDS_CMD_INTERPRETER -Ih:\Project\Versions\5.3\rtids_rellshare\ccgl\trace\commandinterpreter"
-Ic:\sd\tutorial\developer -DRTDS_SOCKET_IP_ADDRESS=192.168.2.101 -DRTDS_SOCKET_PORT=49250 -I. -Wwrite-strings -c -o "RTDS_TCP_Client.o"
h:\project\versions\5.3\rtids_rellshare\ccgl\windows\RTDS_TCP_Client.c"

mingw32-g++ -DRTDS_FORMAT_TRACE -I" -Ih:\project\versions\5.3\rtids_rellshare\ccgl\windows" -Ih:\Project\Versions\5.3\rtids_rellshare\ccgl\trace\formattrace"
-Ih:\Project\Versions\5.3\rtids_rellshare\ccgl\common" -g -DRTDS_SIMULATOR -DRTDS_CMD_INTERPRETER -Ih:\Project\Versions\5.3\rtids_rellshare\ccgl\trace\commandinterpreter"
-Ic:\sd\tutorial\developer -DRTDS_SOCKET_IP_ADDRESS=192.168.2.101 -DRTDS_SOCKET_PORT=49250 -I. -Wwrite-strings -c -o "RTDS_CmdInterpreter.o"
h:\Project\Versions\5.3\rtids_rellshare\ccgl\trace\commandinterpreter\RTDS_CmdInterpreter.c"


mingw32-g++ -DRTDS_FORMAT_TRACE -I" -Ih:\project\versions\5.3\rtids_rellshare\ccgl\windows" -Ih:\Project\Versions\5.3\rtids_rellshare\ccgl\trace\formattrace"
-Ih:\Project\Versions\5.3\rtids_rellshare\ccgl\common" -g -DRTDS_SIMULATOR -DRTDS_CMD_INTERPRETER -Ih:\Project\Versions\5.3\rtids_rellshare\ccgl\trace\commandinterpreter"
-Ic:\sd\tutorial\developer -DRTDS_SOCKET_IP_ADDRESS=192.168.2.101 -DRTDS_SOCKET_PORT=49250 -I. -Wwrite-strings -c -o "RTDS_FormatTrace.o"
h:\Project\Versions\5.3\rtids_rellshare\ccgl\trace\formattrace\RTDS_FormatTrace.c"

mingw32-g++ -o "sPhone.exe" RTDS_encodedMsgData.o RTDS_Env.o PhoneNuberFactory.o pCentral.o RTDS_Start.o pLocal.o RTDS_OS.o RTDS_TCP_Client.o RTDS_CmdInterpreter.o
RTDS_FormatTrace.o h:\Project\Versions\5.3\rtids_rellshare\3rdparty\MinGW\lib\libws2_32.a

### Done.
  
```

### 5.4.3 The SDL-RT debugger

When launched, the SDL-RT debugger will automatically start and initialize the underlying gdb environment. The *SDL-RT debugger* window is started automatically:



*The SDL-RT debugger window*

The SDL-RT debugger is basically a debugger with graphical integration. This window provides snapshots of the overall system.

First we want an MSC trace to see what is happening in the system. Click on the *Start MSC trace* quick button:




An *MSC Tracer* window appears. Note it is not an MSC editor window; the MSC Tracer has been optimized for performance and the displayed trace can not be edited.


Let's start the system; click on 'run' quick button:



Let the system run until all pLocal processes are created by pCentral and their start transition executed:



MSC trace

Note you can detach the execution button bar by dragging it away from the debugger window by its header (the zone looking like this:  ).




The environment is represented by RTDS\_Env process. It is automatically generated by PragmaDev Studio when debugging to represent all external modules. When generating target code it will of course disappear.

Process pCentral dynamically creates 5 instances of pLocal, sends ready message to the environment and goes to idle state. Each pLocal instance then go to idle state. On the left is the value of the system time.

Click on the Stop button to break execution:



The SDL-RT debugger window shows the list of processes with their names (all the same in our case), priority, process id, queue id, number of messages in their respective message queues, SDL-RT internal state as we defined in the diagrams, and the RTOS internal system state if available.



The screenshot shows the PragmaDev Debugger window with the following components:

- Process List Table:**

Name	Prio	SDL id	RTOS id	Msg	SDL-RT state	System state
RTDS_Env	0	0x5220a8	0x18fc	0	RTDS_Idle	N/A
pCentral	0	0x522020	0xd44	0	idle	N/A
pLocal	0	0x521d00	0x2048	0	idle	N/A
pLocal	0	0x521e08	0x20b8	0	idle	N/A
pLocal	0	0x521f10	0x1a58	0	idle	N/A
pLocal	0	0x523f78	0xd40	0	idle	N/A
pLocal	0	0x5247b0	0x132c	0	idle	N/A
- Timer info:**

Owner	Name	Time left
- Semaphores:**

SemId
- Local variables:** (Empty table)
- Textual Trace:**

```

>Task pLocal(0x521e08) prio:0 created by pCentral(0x522020) at: 124 ticks
>Task pLocal(0x521d00) has changed to state idle at: 124 ticks
>Task pLocal(0x521e08) has changed to state idle at: 187 ticks
>Task pLocal(0x521f10) prio:0 created by pCentral(0x522020) at: 187 ticks
>Task pLocal(0x5247b0) prio:0 created by pCentral(0x522020) at: 280 ticks
>Message: ready uniqueId: 1 sent by: pCentral(0x522020) at: 327 ticks
>Task pLocal(0x521f10) has changed to state idle at: 327 ticks
>Task pLocal(0x5247b0) has changed to state idle at: 327 ticks
>Task pCentral(0x522020) has changed to state idle at: 358 ticks
>Message: ready uniqueId: 1 received by: RTDS_Env(0x5220a8) at: 358 ticks
>stop
>

```
- Debugger state:** STOPPED
- Active thread:** 0xed8->Unknown


### SDL-RT debugger window

It can also display information regarding semaphores and timers, local variables and watch variables. The SDL-RT debugger shell gives a textual trace of the events displayed in the MSC.


We are now going to set a breakpoint, simulate a user using one phone to call another one and step in process pCentral.

Let's put a breakpoint in pCentral process. To do so:

- Open pCentral process from the *Project manager*. Double-clicking on its name in the running instances list in the debugger window works too.
- Go to transition getId in state idle using the *transition browser* window on the right:





or the view menu:




The *transition browser* of the *View/Go to* menu will list all SDL-RT states and all transitions in each state to quickly navigate through the system. In our case there is only one state and one transition.


- click on the symbol just after the decision:



- click on  or go to *Debug / Set breakpoint* menu in the *SDL-RT editor*. A breakpoint symbol will be displayed on the side of the selected symbol:




We will now simulate an incoming message from a user. Please note this feature is not available in the *Tasking* integration nor in the *XRAY* integration because these C debuggers can neither execute function calls on target nor simulate interrupts.

- Go to the *SDL-RT debugger* and click on "Send an SDL message to the running system" quick-button 




- The *Send an SDL message* window shows up:



## Send an SDL message window

On the left are listed all possible receiving processes, in the middle all possible messages, i.e. all messages used in the SDL-RT system, and on the right the value of the parameters associated with the selected message.

- Prepare the message to be sent:




The message to be sent is `call`, with the parameter value 2. We will choose the first listed instance of `pLocal` as the receiver. You might want to write down it's PID, since we will send it another message later.


**NB:** it may happen that the first listed instance of `pLocal` has been assigned the phone number 2, in which case the following will not work, as the phone will try to call itself. If this happens, just send again a new `call` message to another `pLocal` instance.

- Click on *Send & close* button.
- Click on *Run* in the *SDL-RT debugger* window,

- The following trace appears in the MSC:



- The SDL-RT editor pops up where the breakpoint was set with the break line in yellow:



The values of the process local variables are automatically displayed in the SDL-RT debugger. For example the phoneNumber variable value is 2:

Local variables	Values
phoneId (Unknown)	(PhoneNumberFactory *) 0x373308
phoneNumber (Unknown)	2
pId (Unknown)	-
index (Unknown)	5


#### Local variables values

- Click on *Auto step until next graphical symbol* button:



That quick button will actually step in the C code until the line in the C file is generated from a graphical symbol. In our case it will only step once.

- The SDL-RT has moved to the next symbol:



- Click on *Step over* button:



- This will step in the C code as any normal C debugger. The text editor opens and displays the next line to execute in the generated C file. Have a look at the generated code to see how legible it is.


```

169 switch(RTDS_currentContext->sdlState)
170 {
171     /* Transitions for state idle */
172     case RTDS_state_idle:
173         switch(RTDS_currentContext->currentMessage->messageNumber)
174         {
175             /* Transition for state idle - message getId */
176             case RTDS_message_getId:
177                 RTDS_MSG_RECEIVE_getId(
178                     phoneNumber);
179                 if ( ! (phoneNumber < NUM_PHONE) )
180                 {
181                     RTDS_MSG_QUEUE_SEND_TO_ID(RTDS_message_errorMsg, 0, NULL, SENDER);
182                     RTDS_SDL_STATE_SET(RTDS_state_idle);
183                     break;
184                 }
185                 else if ( phoneNumber < NUM_PHONE )
186                 {
187                     pId = phoneId->getPid(phoneNumber);
188                     RTDS_MSG_SEND_idMsg_TO_ID(SENDER,
189                                             RTDS_SDL_STATE_SET(RTDS_state_idle);
190                                             pId);
191                     break;
192                 }
193             default:
194                 RTDS_transitionExecuted = 0;
195                 break;
196             /* End of switch on message */
197         }
198         break;
199     default:
200         RTDS_transitionExecuted = 0;
201         break;
202     /* End of switch(RTDS_currentContext->sdlState) */
203     /* ***** */
204     /* $(RTDS_HOME)/share/ccg/windows/bricks/RTDS_Proc_end.c begins */
205     /* PragmaDev RTDS win32 integration */
206     RTDS_TransitionCleanup( RTDS_currentContext, RTDS_sdlStatePrev );
207     /* End of if ( RTDS_currentContext->currentMessage != NULL ) to execute t
208     /* End of for ( ; ; ) */
209 }
210
211 /* $(RTDS_HOME)/share/ccg/windows/bricks/RTDS_Proc_end.c ends */
212 /* ***** */

```

Note it is possible to switch from the SDL source to the generated C source back and forth with the *Search / Go to generated source* and *Search / Generated code <-> source* menus.

- Let the system finish its job: click on Run button.

- Stop the system once it has finished execution:  . The process list is updated with their new states:

Name	Prio	SDL id	RTOS id	Msg	SDL-RT state	System state
RTDS_Env	0	0x3f2fa8	0x920	0	RTDS_Idle	N/A
pCentral	0	0x3f2e90	0x844	0	idle	N/A
pLocal	0	0x3f3070	0xa44	0	connected	N/A
pLocal	0	0x3f3178	0x1334	0	connected	N/A
pLocal	0	0x3f3238	0x10b0	0	idle	N/A
pLocal	0	0x3f3620	0x1094	0	idle	N/A
pLocal	0	0x3f3e30	0xd0	0	idle	N/A

Two instances of the pLocal process are connected.

- It is also possible to change the state of a process. To do so right click on the state you want to change and a drop down menu will list all possible states. Let's change the state of the last instance of pLocal to gettingId for example:


RTDS_Env	0	0x3f2fa8	0x920	0	RTDS_Idle	N/A
pCentral	0	0x3f2e90	0x844	0	idle	N/A
pLocal	0	0x3f3070	0xa44	0	connected	N/A
pLocal	0	0x3f3178	0x1334	0	connected	N/A
pLocal	0	0x3f3238	0x10b0	0	idle	N/A
pLocal	0	0x3f3620	0x1094	0	idle	N/A
pLocal	0	0x3f3e30	0xd0	0	idle	N/A

Time: 8782

Timer info

Owner	Name	Time left



RTDS\_Start  
idle  
connecting  
**gettingId**  
connected  
disconnecting  
RTDS\_Idle


The state is changed on the target and the process list will refresh:

Name	Prio	SDL id	RTOS id	Msg	SDL-RT state	System state
RTDS_Env	0	0x3f2fa8	0x920	0	RTDS_Idle	N/A
pCentral	0	0x3f2e90	0x844	0	idle	N/A
pLocal	0	0x3f3070	0xa44	0	connected	N/A
pLocal	0	0x3f3178	0x1334	0	connected	N/A
pLocal	0	0x3f3238	0x10b0	0	idle	N/A
pLocal	0	0x3f3620	0x1094	0	idle	N/A
pLocal	0	0x3f3e30	0xd0	0	gettingId	N/A

It is recommended to be cautious when changing a task state that way...

- We will now disconnect the 2 instances of pLocal. Click on the Send button

**T0** :



Select the hangUp message with the receiver set to the same pLocal instance as you selected as the receiver of the call message earlier (check with its PID). Then click on Send & close.

- We will now use the key SDL-RT event stepping button: 


This feature runs the system until the next SDL-RT event such as sending or receiving a message, changing SDL-RT state, starting or cancelling a timer... Click on the button and you will see the system executing until the next SDL-RT event and then stop. This is a very nice feature when debugging for the first time.

#### 5.4.4 Verifying the behavior


We will now check if the behavior is the one we expected in the first place. To do so we will use the MSC diff feature.

- Once the execution is finished, close the MSC Tracer and save the trace.
- Go to the Project manager and open the trace.


- Go to the *Diagram / Compare with other diagram...* menu to get the MSC Diff configuration window and set it up as described below:



The first MSC is the execution trace and the second MSC is the normal MSC we have written in the first place. Since normal MSC was not supposed to be thoroughly detailed we will only show and compare messages without considering their parameters. Click *Ok* and you should get the following:



Here you can navigate through the differences, and by selecting *All*, then all of them will be shown in the diagram:



The differences between the MSCs are the dynamic task creation of the pLocal instances. After that the exchange of messages are the same between the dynamic trace and the specification. The SDL-RT system is therefore conform to the normal MSC specification.

You are done with a very simple SDL-RT debugging session. If you want more, do your own system or run the examples delivered in the distribution to see how to manipulate:



- timers,
- semaphores,
- external C header files,
- global variables.

## 5.5 - Prototyping GUI

PragmaDev Studio has a built in support to design simple prototyping interface to ease testing. We will build a very simple one for our phone system to demonstrate its capabilities.

### 5.5.1 GUI editor


Add a Prototyping GUI node in the project and open it:






## Tutorial


The left panel contains the incoming triggers for the GUI, the central panel the GUI itself, and the right panel the outgoing message from the GUI:




Let's add 2 buttons and one LED:




Change their display value in the central panel and their widget name in the right panel in order to recognize them:




Let's say that when the user clicks on the "Call John" button, the GUI sends a call message with parameter set to "2". Select the CallJohn widget on the right panel and right click:




All the available messages in the system are then listed. Select `call` and expand the created sub-tree. The parameters are listed with their corresponding type:




Let's say the parameter value is '2' and let's send `hangUp` without any parameter when clicking on `Hangup`:




On the left panel now, we will add a new trigger. A trigger performs some action on the widgets whenever a message is sent out of the system.. Select the top of the tree and right click to get a list of all the possible triggers:




Let's add the `callConf` trigger. When a trigger is received by the GUI, a case with a set of filters is verified. Let's add a new case:




In our case we won't put any filter, we will just change the color of the LED:




The default action is DISPLAY; you'll have to right click on it to change it to CHANGE\_COLOR. The node in the tree under the action specifies the new color for the widget. It is possible to directly name the basic colors, otherwise the RGB hexa code can be used (e.g #FF8000 is [this color](#)). Let's put the LED back to red when we receive a HangUp confirmation and we're done:




## 5.5.2 Simulation

Let's start the Debugger again and click on the Start prototyping GUI quick button: 

The GUI will start and connect automatically to the system:



Start an MSC trace and run the system. Click on the "Call John" button, that should send the `call` message with parameter value set to 2, the `callConf` should be received by the GUI, and the LED should be set to green:



For a more advanced GUI, please have a look at the AccessControl system in the Developer example directory.

## 5.6 - Conclusion

During this tutorial we have been through the basics of the following:

- SDL-RT;
- Project manager;
- SDL-RT editor;
- MSC editor;
- Code generation;

- SDL-RT debug including the three stepping modes:
  - SDL-RT key event,
  - SDL-RT graphical,
  - textual;
- Conformance checking;
- Prototyping GUI.

As a result you saw SDL-RT has the preciseness of C language with the graphical abstraction of SDL and UML perfectly suited to real time systems showing key concepts such as tasks, semaphores, timers, messages in a single consistent development environment.


Now it is time for you to work on a real real time system!

## 6 - Automatic documentation generation


Let's now have a look at how to document our system. PragmaDev Studio has an automatic documentation generator that generates OpenDocument (OpenOffice), RTF (Microsoft Word), HTML, and SGML documents. In this tutorial we will generate an OpenDocument as it is very similar to generating an RTF document. The basic idea is to document while you are modeling your system in SDL, and when you are done just generate the documentation for a word processor or a browser.

### 6.1 - Publications


Let's first define what is important to document in our system and put it in a publication. For example let's consider the architecture of the system should be further documented:



Get to the corresponding diagram and go to the *Export* menu. In that we will export the whole partition, to do so select *Export/publish partition...*




The *Export/publish* window opens:






Let's give our publication a name, the *Doc* type, and check the *Save as publication* box:




Select the *Texts* tab. The two editors here allow you to type the texts that will be generated before and after the diagram when generating the documentation. Let's type a few words to document the diagram with the pre-defined paragraph and character styles:




We want the NUM\_PHONE identifier to appear as code, and also to be listed in the document index. To do so, select the text, and apply to it the code-index-entry character style that is listed in the "f:" selector above the text.

When done click *OK*.



Let's now document a transition. Open the pLocal process and go to the Connected state:



Go to the *Export* menu and select *Export/publish selected state or transition...*:





This will export the state with all the connected inputs as a publication. Let's document the state:




Please note the publications are saved within the diagram so it is important to also save the diagrams.

## 6.2 - Documentation


Let's now go back the *Project manager* and create a new item of type *Document*:



Let's open the *Document Design*:




Select Design and right-click to add a sub-section:




This sub-section will actually be the first chapter of the generated documentation. Adding other sub-sections at the same will generate other chapters. Adding sub-sections to


this section will generate sub-chapters. Let's type the section title and add some contents to the section with the + button:




In order to have the *Diagram publication reference* available, the diagrams containing publications must be opened. So in our case the top level architecture diagram and the pLocal process should be open in order to move on. The following window will pop up:



The *Styled* text allows to insert plain text in the documentation. To insert one of the diagram publication, select *Diagram publication reference*. The window should then look like this:




Select the appropriate *Publication diagram* and *Publication name* to insert in the *Document*. Then create another sub-section in the document with the other publication:





## 6.3 - Automatic generation


Go to *Document / Export as / Open Document Format*:




An OpenDocument is actually a zip file that contains several files among which:

- one is the document itself as an XML file,
- one describes the styles used in the document also as an XML file.


In order to generate the full OpenDocument zip file, PragmaDev Studio requires a template file. We suggest you use the one that is provided in the Specifier / AccessControl example directory:





Now we will create an OpenDocument container for our generated document in which we can set a title, introduce a table of contents, and an index. To do so, let's start OpenOffice :




Create a new Master document with *File / New / Master document* menu:




Type the title, insert a page break, and insert a table of content with the *Navigator* window:




In the same Navigator window, insert the OpenDocument we have just generated:




And insert an index:




It is possible to drag and drop sections in the Navigator window to get the right order:




It is possible to add other sections or other external documents in the master document.


When you further document your system, to update the generated documentation: open your Pragmadev Studio document, export it as an OpenDocument, replacing the existing one, and that's it! The OpenOffice master document will be updated by itself as well as its table of contents and index and ready to be printed. You can also set the OpenDocument export as the default one and just press the  button in the document editor:




Please note it is also possible to automatically generate all publications and a document based on the project architecture. To do so, create a new document:




Open it and go to the Document / Auto-generate from project... menu:



Select the level for each publication:



And a full document is generated:



If you already have existing publications at the proper level for the auto-generated document, they will be reused. If a publication is missing, it will be created. You can add explanation texts before and/or after the created publications after creation.